

# WGM SOFTWARE USER MANUAL

Author: Sami Dhiab


Revision : 0.0.1

Log: 19.01.2023

## I. Download


1. Download the latest version from [here]([https://github.com/theion-batteries/soft\\_wgm\\_installer\\_update](https://github.com/theion-batteries/soft_wgm_installer_update))

- a. Click on **Code** and Download ZIP




## II. Install

1. Run the installer wgm\_pkg.exe



2. Be sure to install the software under C:/program files/wgm\_pkg/ (for path matching)



3. Install VC\_redist.x64 (if not already installed on windows) to avoid missing dependencies.

### III. Run

1. After successful installation, navigate to the installation folder.
2. Run the wgm\_app.exe inside C:/program files/wgm\_pkg/bin/debug/ as admin the first time.

Windows (C:) > Program Files > wgm\_pkg > bin > Debug

Name	Date modified	Type	Size
d3dcompiler_47.dll	18/01/2023 16:52	Application extens...	4.419 KB
Qt6Guid.dll	18/01/2023 16:52	Application extens...	22.812 KB
Qt6Svgd.dll	18/01/2023 16:52	Application extens...	1.044 KB
Qt6Widgets.dll	18/01/2023 16:52	Application extens...	15.891 KB
Qt6Cored.dll	18/01/2023 16:52	Application extens...	15.087 KB
wgms_app.exe	18/01/2023 16:52	Application	4.411 KB
MeteorCLS.dll	17/01/2023 11:26	Application extens...	48 KB
PrintEngine.dll	17/01/2023 11:26	Application extens...	10.231 KB
PrinterInterface.dll	17/01/2023 11:26	Application extens...	1.336 KB
PrinterInterfaceCLS.dll	17/01/2023 11:26	Application extens...	26 KB
CmnLib.dll	24/10/2022 13:27	Application extens...	82 KB
KeyUsbDrv.dll	24/10/2022 13:27	Application extens...	95 KB
LKIF2.dll	24/10/2022 13:27	Application extens...	45 KB
concr140.dll	07/10/2022 17:23	Application extens...	310 KB
msvc140.dll	07/10/2022 17:23	Application extens...	558 KB
msvc140_1.dll	07/10/2022 17:23	Application extens...	25 KB
msvc140_2.dll	07/10/2022 17:23	Application extens...	183 KB


3. Optional: place a shortcut on the desktop

## IV. User Interface Overview

### A. Process Tabs


#### 1. Main Tab

The Main Tab provides the list of all processes. User can select one process from the list and click on **->execute process** to execute that process automatically. The progress bar is updated in real time. Once the process finished or aborted, the time elapsed display is updated with the value in seconds. By clicking on **->execute all** the processes will run automatically in corresponding order.




## 2. Heating Process Tab

By clicking on **->connect heating dev** the application will try to establish connection with heating device and inform the user by changing the variable heating\_ready from **false** to **true** if the connection is success. After successful connection, the user can send direct command to the heating device to manually alter settings. By writing the command in the white text field and pressing enter, the cmd\_given field is updated and heating\_response field will be updated with the device response. By pressing the **-> run heating process**, the process will start automatically. The process\_finished variable will be updated to true once the process finishes. Process time elapsed display is updated upon finishing or abort. Temperature display will notify user with temperature in real time.



### 3. Sinking Process Tab

By clicking on **->connect motion axis** the application will try to establish connection with motion axis device and inform the user by changing the variable `axis_ready` from **false** to **true** if the connection is success. Same apply for the **->connect distance sensor**. After successful connection, the user can send direct command to the axis motion device to manually interact with it. By writing the command in the white text field and pressing enter, the `cmd_given` field is updated and `axis_response` field will be updated with the device response. The displays will notify user about each parameter in real time. The algorithm part is helpful to test certain process step individually. By clicking on **->move\_down\_until\_sensor\_data\_valid** the algorithm is executed, and the displays are updated on the fly. The algorithms and process steps are explained in different sections. By pressing the **-> run Sinking process**, the process will start automatically. The `process_finished` variable will be updated to true once the process finishes. Process time elapsed display is updated upon finishing or abort.




#### 4. CNT Alignment Process Tab

By clicking on **->connect motion axis** the application will try to establish connection with motion axis device and inform the user by changing the variable **axis\_ready** from **false** to **true** if the connection is success. Same apply for the **->connect cnt dispenser** and **->connect high\_voltage**. After successful connection, the user can send direct command to the choosen device to manually interact with it. By writing the command in the white text field and pressing enter, the **cmd\_given** field is updated and response field will be updated with the device response. The displays will notify user about each parameter in real time. The algorithm part is helpful to test certain process step individually. By clicking on **->move\_down\_to\_center** the algorithm is executed, and the displays are updated on the fly. The algorithms and process steps are explained in different sections. By pressing the **-> run aligning process**, the process will start automatically. The **process\_finished** variable will be updated to true once the process finishes. Process time elapsed display is updated upon finishing or abort.




## 5. Cooling Process Tab

By clicking on **->connect motion axis** the application will try to establish connection with linear motion axis device and inform the user by changing the variable `axis_ready` from **false** to **true** if the connection is success. Same apply for the **->connect rotation axis** and **->connect printhead dev**. After successful connection, the user can send direct command to the choosen device to manually interact with it. By writing the command in the white text field and pressing enter, the `cmd_given` field is updated and response field will be updated with the device response. The displays will notify user about each parameter in real time. The algorithm part is helpful to test certain process step individually. By clicking on **->linear\_move\_home** the algorithm is executed, and the displays are updated on the fly. The algorithms and process steps are explained in different sections. By pressing the **-> run cooling process**, the process will start automatically. The `process_finished` variable will be updated to true once the process finishes. Process time elapsed display is updated upon finishing or abort.



## 6. Extracting Process Tab

The extracting process tab is the reverse operation of the sinking process and has a similar tab view. Please refer to the sinking process tab.






## B. Menu Tabs


### 1. File Menu

User can create an account by providing a username and password. The user data are saved inside a database. After creating account, user can login and start using the application. By clicking on new experiment, the user will create a recording of all parameters for each process. Once finished, user can save the experiment to save data inside the database. By clicking open experiment, user can have access and retrieve previous data of an experiment. By clicking logout the current user is logged out.




## 2. Edit Menu

Each Process has predefined default parameters. User can change these parameters before each process execution.



As example, by clicking on whs\_config.yaml, the configuration file for sinking process will be opened.




Details about each parameter are explained in different sections.

3. View Menu  
Under Construction.


4. Build Menu  
Under Construction.

5. Debug Menu

By clicking on Debug->open debug console, user can get log messages and capture any errors.



For example, by clicking on ->connect motion axis the message connecting controller to axis server is indicated.



## 6. Analyze Menu

Under Construction.

## 7. Tools Menu

Under Construction.

## 8. Window Menu

Under Construction.

## 9. Help Menu

By clicking on Help->documentation, the user manual will be opened as pdf.

By clicking on Help->grbl, the link for grbl manual will be opened inside the browser.

By clicking on Help->update, the software will check for latest update and prompt for install.

